



ThreadWorks V1.0.2

Recommended Installation for Your Platform:

[Download Installer for Windows...](#)

Installer created with [InstallAnywhere®](#) by Zero G Software, Inc. Copyright 2001. [www.ZeroG.com](#)

Available Installers

	Platform	without Java VM	Instructions
>	 Windows	Download (1.3M)	View
	 AIX	Download (1.2M)	View
	 Solaris	Download (1.2M)	View
	 Linux	Download (1.2M)	View
	 HP-UX	Download (1.2M)	View
	 Unix	Download (1.2M)	View
	 Other Java-enabled Platforms	Download (1.1M)	View

Windows Instructions:

Instructions

- After downloading, double-click **ThreadWorksV1.0.2.exe**

Notes

- ⚡ You may need to install a Java 1.1.8 (or later) virtual machine. You can download one from [Sun's Java web site](#).

[\(Go To Top\)](#)

AIX Instructions:

Instructions

- ⚡ After downloading open a shell and, `cd` to the directory where you downloaded the installer.
- ⚡ At the prompt type: `sh ./ThreadWorksV1_0_2.bin`

Notes

- ⚡ You need to install a Java 1.1.4 (or later) virtual machine. You can download one from [Sun's Java web site](#).

[\(Go To Top\)](#)

Solaris Instructions:

Instructions

- ⚡ After downloading open a shell and, `cd` to the directory where you downloaded the installer.
- ⚡ At the prompt type: `sh ./ThreadWorksV1_0_2.bin`

Notes

- ⚡ You need to install a Java 1.1.4 (or later) virtual machine. You can download one from [Sun's Java web site](#).

[\(Go To Top\)](#)

Linux Instructions:

Instructions

- ⌘ After downloading open a shell and, `cd` to the directory where you downloaded the installer.
- ⌘ At the prompt type: `sh ./ThreadWorksV1_0_2.bin`

Notes

- ⌘ You need to install a Java 1.1.4 (or later) virtual machine. You can download one from [Sun's Java web site](#) or contact your OS manufacturer.

[\(Go To Top\)](#)

HP-UX Instructions:

Instructions

- ⌘ After downloading open a shell and, `cd` to the directory where you downloaded the installer.
- ⌘ At the prompt type: `sh ./ThreadWorksV1_0_2.bin`

Notes

- ⌘ You need to install a Java 1.1.4 (or later) virtual machine. You can download one from [Sun's Java web site](#) or contact your OS manufacturer.

[\(Go To Top\)](#)

Unix Instructions:

Instructions

- ⌘ After downloading open a shell and, `cd` to the directory where you downloaded the installer.
- ⌘ At the prompt type: `sh ./ThreadWorksV1_0_2.bin`

Notes

- ⌘ You need to install a Java 1.1.4 (or later) virtual machine. You can download

one from [Sun's Java web site](#) or contact your OS manufacturer.

- ⌘ If you do not have a Java virtual machine installed, be sure to download the package above which includes one. Otherwise you may need to download one from [Sun's Java web site](#) or contact your OS manufacturer.

[\(Go To Top\)](#)

All Other Platforms Instructions:

Instructions (Unix or Unix-like operating systems)

- ⌘ For Java 2, after downloading, type
`java -jar ThreadWorksV1_0_2.jar`
- ⌘ For Java 1.1, after downloading, type
`jre -cp ThreadWorksV1_0_2.jar install`
- ⌘ If that does not work, try
`java -classpath [path to] classes.zip:ThreadWorksV1_0_2.jar install`
- ⌘ If that does not work either, on sh-like shells, try
`cd [to directory where ThreadWorksV1_0_2.jar is located]`
`CLASSPATH=ThreadWorksV1_0_2.jar`
`export CLASSPATH`
`java install`
- ⌘ Or for csh-like shells, try
`cd [to directory where ThreadWorksV1_0_2.jar is located]`
`setenv CLASSPATH ThreadWorksV1_0_2.jar`
`java install`

Instructions (for other platforms)

- ⌘ Be sure you have Java 1.1.6 or later installed. You can download Java from [Sun's site](#)
- ⌘ In a console window, change to the directory where you downloaded `ThreadWorksV1_0_2.jar` to before running the installer
- ⌘ Your operating system may invoke Java in a different way. To start the installer, add `ThreadWorksV1_0_2.jar` to your `CLASSPATH`, then start the main class of the installer named `install`

[\(Go To Top\)](#)

InstallAnywhere is a registered trademark of Zero G Software, Inc.
Mac OS is a registered trademark of Apple Computer, Inc.
Solaris and Java are trademarks of Sun Microsystems, Inc.
Windows is a registered trademark of Microsoft Corporation.
All other marks are properties of their respective owners.